

Timed products

How to make a product appear on the menu only between two times of day, for example breakfast from 08:30 until 12:00.

Screenshots taken on a live till at app.posso.co.uk, 9 October 2026. Your products will be different. On some sites the side button is labelled **Stock Management**.

What a timed product does


A timed product is on the menu only between its **start time** and its **stop time**, every day. Outside those times it disappears from the tills, the kiosks, online ordering and the menu boards by itself. Nobody has to hide it and nobody has to put it back the next morning.

The short version

- Tap **STOCK COUNTS**, open the category and tap **EDIT** next to the product.
- Tap the **Timed** tab and choose **TIMED**.
- Pick the start time and the stop time.
- Tap **SAVE PRODUCT**.


1 Open Stock Counts

On the till, tap the orange **STOCK COUNTS** button at the top of the left side bar.



2 Find the product and tap EDIT

Tap the category (here **Breakfast & Bakery**), or use **Search products**. Then tap **EDIT** on the product's row. This time it is EDIT you want, not STOCK.



3 Tap the Timed tab

The product editor opens. Tap **Timed** in the row of tabs. A dot on the tab means the product is already timed.

EDIT PRODUCT

5 item b/fast - contains 1 meat item

£4.20 · Breakfast & Bakery

MENU **ON** HIDDEN SALE **AVAILABLE** **88** SHOW ON **TILL** **KIOSK** **ONLINE** **BOARD**

PRODUCT PRICING **TIMED** PRINTING PORTIONS MODIFIERS ATTRIBUTES RECIPE STOCK CODES

DETAILS
What this product is called and where it lives on the menu.

PRODUCT NAME
5 item b/fast - contains 1 meat item

CATEGORY
Breakfast & Bakery

DESCRIPTION

IMAGE

APPEARANCE
Till / kiosk tile colours. Leave default if you use photos.

BACKGROUND **TEXT COLOUR**

CANCEL **SAVE PRODUCT**

Leave the top row alone

The **Menu**, **Sale** and **Show on** switches at the top are separate settings. You do not need them for timing.

4 Choose Timed and set the times

Tap **TIMED**. Pick the **Start time** and the **Stop time**: hour on the left, minutes on the right, in the 24-hour clock and in 5-minute steps. The line underneath reads the times back in plain words, for example "On the menu from 08:30 until 12:00 each day." Check it says what you mean.

EDIT PRODUCT
5 item b/fast - contains 1 meat item
E4.20 · Breakfast & Bakery

MENU **ON** HIDDEN SALE **AVAILABLE** 88 SHOW ON **TILL** KIOSK ONLINE BOARD

PRODUCT PRICING **TIMED** PRINTING PORTIONS MODIFIERS ATTRIBUTES RECIPE STOCK CODES

TIMED
A timed product is only on the menu between its start and stop times. Outside them it is not shown on tills, kiosks, online ordering or the menu board.

NOT TIMED **TIMED**

START TIME 08 : 30 **STOP TIME** 12 : 00

On the menu from 08:30 until 12:00 each day.

CANCEL **SAVE PRODUCT**

5 Save

Tap **SAVE PRODUCT**. Tap **CANCEL** instead if you do not want to keep the change. Then tap **✕ CLOSE** to go back to the till.

The other tills, the kiosks and the menu boards pick the change up by themselves, usually within a minute or two.

How the times work

Start 08:30, stop 12:00	On the menu from 08:30. Gone at 12:00 exactly, not 12:01.
Start later than stop (22:00 to 02:00)	Runs over midnight: on from 22:00 until 02:00 the next morning.
Start and stop the same	No window at all: the product is on the menu all day.
A time left blank	The till will not save. Set both times, or switch back to Not timed.

To stop timing a product

Open the **Timed** tab, tap **NOT TIMED** and save. The product is then on the menu all day. The old times are remembered, so switching it back to Timed brings them back.

Good to know

- **Already in a basket:** an item rung through before the stop time stays in the basket and can be paid for after it.
- **Online orders:** a customer who put the item in their online basket before the stop time can still finish that order.
- **Can't see a product?** Check the clock first. If it is outside its times, that is why it is missing.
- **Sold out early?** Timing is not for that. Set the stock count to 0 instead (see the Stock Counts guide).
- **No Stock Counts button:** your login does not have permission. Ask your manager, who can also set times from the back office under Products.